

Tektronix RSA Device
MATLAB Driver
User Guide
API Build 3.9.0029

Version 2.02

Table of Contents

Overview.....	1
Requirements	1
Installation.....	1
How to Use the Driver	2
Example: Generate IQ Data	3
Appendix A: Driver Properties	4
Appendix B: Driver Functions	6
Appendix C: Error Values.....	15
Appendix D: DPX GetFrameBuffer.....	16
Appendix E: DPX GetSettings.....	17
Appendix F: DPX GetSogramSettings	17
Appendix G: IQ Block GetIQAcqInfo	17
Appendix H: IQ Stream GetDiskFileInfo.....	17
Appendix I: IQ Stream GetIQData.....	18
Appendix J: Spectrum GetLimits.....	18
Appendix K: Spectrum GetSettings	18
Appendix L: Spectrum GetTraceInfo	19
Appendix M: Spectrum SetSettings.....	19
Appendix N: Power GetHWStatus	19

Overview

The RSA_API MATLAB Driver allows communication between MATLAB and RSA API. The driver uses a generic driver from MATLAB's Instrument Control Toolbox to make individual calls to the API. This driver supports version 3.9.0029 of the API.

Requirements

The following hardware, software and files are needed to use the RSA_API MATLAB driver.

1. RSA device. Supported models: 306, 306B, 503A, 507A, 603A, 607A
2. MATLAB and the Instrument Control Toolbox. (MATLAB R2015b has been tested).
3. Version 3.9.0029 of the RSA API, included in the MLTBX package.
4. MATLAB instrument driver file (RSA_API_Driver.mdd), included in the MLTBX package.

Installation

MATLAB and the Instrument Control Toolbox, are assumed to be previously installed. Add the RSA MATLAB Driver package to MATLAB by running the "Tektronix USB Spectrum Analyzer Driver.mltbx" installer, or by using the "Get Add-Ons" menu in MATLAB. The API installer, examples, and documentation will be added to your Documents\MATLAB\Add-ons\Toolboxes folder.

An installer for the Tektronix RSA API is included in this package. Please run RSA_API_Install.m to install the API, or run the setup.exe file from the RSAAPI-64_3.9.0029 folder if the API has not yet been installed.

The MATLAB driver will look in the default install location of C:\Tektronix\RSA_API for the API files. If you installed the API in a different location, you will need to change the driver path to point to the new location:

1. Open the RSA_API_Driver.mdd in the MATLAB Instrument Driver Editor. See Figure 1.
2. Change the default value of the apiIncludePath and apiLibPath properties. See Figure 2.

Fig 1. Open Driver Editor





Fig 2. Modify Default Properties



How to Use the Driver

Using the Driver requires the following basic steps:

1. Create the device object.
2. Connect to the device object.
3. Set/Get properties or invoke functions.
4. Disconnect from the device object.
5. Delete and clear the device object from memory.

Example of the following basis steps:

1. See Installation section.
2. Create the device object using the `icdevice('driver')` function.
 - a. **'driver'** is the file name for of the MATLAB Instrument Driver.
 - i. **File:** Use this optional parameter for file playback

```
device = icdevice('RSA_API_Driver');  
device = icdevice('RSA_API_Driver', 'File');
```

3. Connect the object to the driver with the `connect(device)` function.
 - i. **device** is the device object created in Step 2.

```
connect(device);
```

4. Set/ Get properties or invoke functions.
 - a. Set properties using the `set(obj, 'propertyName', propertyValue)` function.
 - i. **obj** is the device group object.

```
set(device.Configure, 'CenterFreq', 2.4453e9);
```

- b. Get properties using the `get(obj, 'propertyName')` function.

```
centerFrequency = get(device.Configure, 'CenterFreq');
```

- c. Invoke functions using the `invoke(obj, 'functionName', input1, input2, ...)` function.

```
invoke(device.Device, 'Run');
```

5. Disconnect from the device object using the `disconnect(device)` function.

```
disconnect(device);
```

6. Delete and clear the device object from memory.

```
delete(device);  
clear('device');
```

Example: Generate IQ Data

The following script provides an example that generates IQ data with the MATLAB driver.

```
%Create the device object
dev = icdevice('RSA_API_Driver');

%Connect to the device object
connect(dev);

%Set the center frequency to 2.4453GHz
set(dev.Configure, 'CenterFreq', 2.4453e9);

%Set the reference level to -60dB
set(dev.Configure, 'ReferenceLevel', -60);

%Set the IQ record length to 5000 samples
set(dev.Iqblock, 'IQRecordLength', 5000);

%Begin data acquisition
invoke(dev.Device, 'Run');

%Wait for the IQ data to be ready. It has a timeout value of 5000ms
invoke(dev.Iqblock, 'WaitForIQDataReady', 5000);

%Get IQ data. The start index is set to 0 and the record length is 5000 samples.
[I, Q] = invoke(dev.Iqblock, 'GetIQDataDeinterleaved', 0, 5000);

%Multiply the Q data by sqrt(-1) to make it imaginary
Q = Q*1i;

%Add the I and Q arrays together to get IQ data
IQ = I+Q;

%Stop data acquisition
invoke(dev.Device, 'Stop');

%Disconnect from the device object
disconnect(dev);

>Delete and clear the device object from memory
delete(dev);
clear('dev');
```

Appendix A: Driver Properties

Table 1. Property Value Notation

Notation	Description
{x,y,z}	Set of discrete values: x, y and z.
[x,z]	Continuous values between x and z, inclusive.
[x:z]	Discrete values in increments of 1 between x and z.
[x:y:z]	Discrete values in increments of y between x and z.

Table 2. Audio Properties

Property Name	Description	Values
FrequencyOffset	Set or query a frequency offset from center frequency.	See RSA_API documentation for more information.
Mode	Set or query audio demodulation mode.	{'ADM_FM_8KHZ', 'ADM_FM_13KHZ', 'ADM_FM_75KHZ', 'ADM_FM_200KHZ', 'ADM_AM_8KHZ'}
Mute	Set or query whether audio mute is enabled or disabled.	{true, false}
Volume	Set or query volume level.	[0, 1]

Table 3. Configure Properties

Property Name	Description	Values
AutoAttenuationEnable	Set or query whether auto gain is enabled or disabled.	{true, false}
CenterFreq	Set or query center frequency.	See RSA_API documentation for more information.
ExternalRefEnable	Set or query whether external reference is enabled or disabled.	{true, false}
PreamplifierEnable	Set or query whether preamp is enabled or disabled.	{true, false}
ReferenceLevel	Set or query reference level.	See RSA_API documentation for more information.
RFAttenuator	Set or query whether RF attenuator is enabled or disabled.	{true, false}

Table 4. DPX Properties

Property Name	Description	Values
Enable	Set or query whether DPX is enabled or disabled.	{true, false}

Table 5. GNSS Properties

Property Name	Description	Values
AntennaPower	Set or query whether antenna power is enabled or disabled.	{true, false}
Enable	Set or query whether GNSS is enabled or disabled.	{true, false}

Table 6. IQBlock Properties

Property Name	Description	Values
IQBandwidth	Set or query IQ bandwidth.	[0, 40 MHz]
IQRecordLength	Set or query amount of IQ data samples in each data acquisition.	See RSA_API documentation for more information.

Table 7. Spectrum Properties

Property Name	Description	Values
Enable	Set or query whether spectrum is enabled or disabled.	{true, false}

Table 8. Trigger Properties

Property Name	Description	Values
IFPowerLevel	Set or query IF power detection level.	See RSA_API documentation for more information.
TriggerMode	Set or query trigger mode.	{'freeRun', 'triggered'}
Position	Set or query trigger position.	[0%, 100%]
Source	Set or query trigger source.	{'TriggerSourceExternal', 'TriggerSourceIFPowerLevel'}
Transition	Set or query trigger transition mode.	{'TriggerTransitionLH', 'TriggerTransitionHL', 'TriggerTransitionEither'}

Table 9. Trkgen Properties

Property Name	Description	Values
Enable	Set or query whether tracking generator is enabled or disabled.	{true, false}
OutputLevel	Set or query output level of tracking generator.	See RSA_API documentation for more information.

Appendix B: Driver Functions

Table 10. Alignment Functions

Function Name	Description	Inputs	Outputs
GetAlignmentNeeded	Determine if an alignment is needed.	None	needed: returns true if alignment is needed.
RunAlignment	Run alignment for device.	None	None
GetWarmupStatus	Determine warm up status of device.	None	warmUp: returns true if device is warm up.

Table 11. Audio Functions

Function Name	Description	Inputs	Outputs
GetData	Store audio data in data array.	inSize : maximum number of audio samples.	data : an array of audio data. outSize : number of audio samples in array.
GetEnable	Determine if audio is playing.	None	enable : returns true if audio is streaming to speaker.
Start	Start streaming audio speaker.	None	None
Stop	Stop streaming audio speaker.	None	None

Table 12. Configure Functions

Function Name	Description	Inputs	Outputs
GetExternalRefFrequency	Return the external reference frequency in Hz.	None	extFreq : external reference frequency.
GetMaxCenterFreq	Return maximum frequency of RSA unit in Hz.	None	maxCF : maximum center frequency.
GetMinCenterFreq	Return minimum frequency of RSA unit in Hz.	None	minCF : minimum center frequency.
Preset	Set device to preset values. See RSA_API documentation for more information.	None	None

Table 13. Device Functions

Function Name	Description	Inputs	Outputs
Connect	Connect RSA device.	deviceId : number between 0-19, indicating RSA device connected by USB 3.0	None
Disconnect	Disconnect RSA device.	None	None
GetAPIVersion	Return API version number of device.	None	apiVersion : API version number.
GetDeviceNomenclature	Return name of device.	None	nomenclature : name of device.
GetDeviceNomenclatureW	Return wide name of device.	None	nomenclature : name of device.
GetDeviceSerialNumber	Return serial number of device.	None	serialNum : serial number of device.
GetEnable	Return data acquisition status of device.	None	enable : returns true if data acquisition is running.
GetEventStatus	Obtain event status of device.	eventId : desired event to determine if occurred.	eventOccurred : returns true if event occurred. eventTimestamp : timestamp of event.
GetFPGAVersion	Return FPGA version number of device.	None	fpgaVersion : FPGA version number.
GetFWVersion	Return firmware version number of device.	None	fwVersion : firmware version number.
GetHWVersion	Return hardware version number of device.	None	hwVersion : hardware version number.
OverTemperatureStatus	Determine if device is over temperature.	None	overTemperature : return if device is over temperature
PrepareForRun	Prepare device for data transfer.	None	None
Reset	Reset RSA device.	deviceId : RSA device being reset.	None
Run	Start data acquisition.	None	None
Search	Search for RSA devices connected to PC.	None	numDevicesFound : number of devices found. deviceIDs : an array of device IDs. deviceSerial : device serial number. deviceType : name of device.
StartFrameTransfer	Start data transfer. Call PrepareForRun first.	None	None
Stop	Stop data acquisition.	None	None

Table 14. DPX Functions

Function Name	Description	Inputs	Outputs
Configure	Enable or disable DPX spectrum and spectrogram.	enableSpectrum: enable/disable DPX spectrum. enableSpectrogram: enable/disable DPX spectrogram.	None
FinishFrameBuffer	This function must be called before getting a new frame buffer.	None	None
GetFrameBuffer	Return latest Frame Buffer.	None	frameBuffer: see Appendix D: DPX GetFrameBuffer.
GetFrameInfo	Return live update of frame count and FFT count.	None	frameCount: frame count fftCount: FFT count
GetRBWRange	Return maximum and minimum RBW values.	fspan: span used to calculate RBW limits.	minRBW: minimum RBW allowed. maxRBW: maximum RBW allowed.
GetSettings	Return current DPX spectrum settings.	None	dpxSettings: see Appendix E: DPX GetSettings.
GetSogramHiResLine	Return the specified spectrogram line after the system has stopped acquiring DPX data.	lineIndex: sogram line to retrieve. tracePoints: length of sogram line to retrieve. firstValidPoint: first point to retrieve from the sogram line. Set to 0 to retrieve the whole line.	vData: array containing the sogram line data. dataSF: scaling factor for the sogram line data.
GetSogramHiResLineCountLatest	Return how many spectrogram lines are available.	None	lineCount: number of sogram lines.
GetSogramHiResLineTimestamp	Return timestamp of specified sogram line.	lineIndex: sogram line to retrieve a timestamp for.	timestamp: timestamp of the specified sogram line.
GetSogramHiResLineTriggered	Determine if trigger event occurred at specified sogram line.	lineIndex: sogram line to retrieve a trigger event for.	triggered: returns true if trigger event occurred for the specified sogram line.
GetSogramSettings	Return current DPX spectrogram settings.	None	sogramSettings: Appendix F: DPX GetSogramSetting S.
IsFrameBufferAvailable	Determine availability of DPX frame.	None	frameAvailable: returns true if frame is available.
Reset	Reset DPX processor to default values. See	None	None

	RSA_API documentation for default values.		
SetParameters	Set DPX processor parameters.	fspan: span in Hz. rbw: resolution bandwidth in Hz. bitmapWidth: width of bitmap in pixels. tracePtsPerPixel: number of trace points in spectrum trace for each bitmap pixel. yUnit: vertical units for bitmap. yTop: vertical upper limit for bitmap. yBottom: vertical lower limit for bitmap. infinitePersistence: enable/disable for every data point to persist. persistenceTimeSec: amount of time in seconds that previous signal will persist. showOnlyTrigFrame: enable/disable to show only trigger frames.	None
SetSogramParameters	Set parameters for DPX spectrogram.	timePerBitmapLine: amount of time per bitmap line. timeResolution: amount of time each sogram line represents. maxPower: maximum power of sogram. minPower: minimum power of sogram.	None
SetSogramTraceType	Set spectrogram trace type.	traceType: trace type to set for sogram.	None
SetSpectrumTraceType	Set spectrum trace type for specified spectrum trace.	traceIndex: specify trace to be set. 0, 1, or 2 type: trace type to set for spectrum trace.	None
WaitForDataReady	Wait for DPX data to be ready, otherwise timeout.	timeoutMsec: maximum time to wait for data to be ready, in milliseconds.	ready: returns true if the data is ready.

Table 15. GNSS Functions

Function Name	Description	Inputs	Outputs
ClearNavMessageData	Clear navigation message in buffer.	None	None
Get1PPSTimestamp	Return 1PPS timestamp.	None	isValid: returns true if 1PPS is valid. timestamp1PPS: timestamp of 1PPS.
GetHWInstalled	Determine if GNSS hardware is installed.	None	installed: returns true if GNSS hardware is installed.
GetNavMessageData	Return navigation message in buffer.	None	msgLen: length of navigation message. message: NMEA message.

Table 16. IF Stream Functions

Function Name	Description	Inputs	Outputs
GetActiveStatus	Determine if device is writing to disk.	None	active: returns true while streaming to disk.
SetDiskFileCount	Set number of files to generate.	count: number of files to stream to disk.	None
SetDiskFileLength	Set how long to record to disk in milliseconds.	msec: number of milliseconds to record data.	None
SetDiskFileMode	Set mode of IF stream.	mode: streaming mode.	None
SetDiskFilenameBase	Set name of file.	base: name of file streamed to disk.	None
SetDiskFilenameSuffix	Set suffix of file appended to name of file.	suffixCtl: suffix of file.	None
SetDiskFilePath	Set path of file.	path: location to save file.	None
SetEnable	Enable or disable streaming ADC to disk.	enable: enable/disable to stream ADC data to disk.	None

Table 17. IQ Block Functions

Function Name	Description	Inputs	Outputs
AcquireIQData	Start data acquisition.	None	None
GetIQAcqInfo	Return current IQ header data.	None	header: see Appendix G: IQ Block GetIQAcqInfo.
GetIQData	Return IQ data in interleaved format. startIndex and length should not exceed RecordLength.	startIndex: starting index of IQ record. length: number of IQ samples to acquire.	iqData: I and Q data at alternating indexes in array.
GetIQDataCplx	Return IQ data in interleaved format. startIndex and length should not exceed RecordLength.	startIndex: starting index of IQ record. length: number of IQ samples to acquire.	iqData: I and Q data at alternating indexes in array.
GetIQDataDeinterleaved	Return IQ data in deinterleaved format. startIndex and length should not exceed RecordLength.	startIndex: starting index of IQ record. length: number of IQ samples to acquire.	iData: I data array. qData: Q data array.
GetIQSampleRate	Return sample rate. Based on bandwidth.	None	iqSampleRate: sample rate of device.
GetMaxIQBandwidth	Return maximum bandwidth of device.	None	maxBandwidth: maximum bandwidth.
GetMaxIQRecordLength	Return maximum record length of device.	None	maxSamples: maximum record length.
GetMinIQBandwidth	Return minimum bandwidth of device.	None	minBandwidth: minimum bandwidth.
WaitForIQDataReady	Wait for IQ data to be ready, otherwise timeout.	timeoutMsec: maximum time to wait for data to be ready, in milliseconds.	ready: returns true if data is ready.

Table 18. IQ Stream Functions

Function Name	Description	Inputs	Outputs
ClearAcqStatus	Reset sticky bits in iqinfo for GetIQData.	None	None
GetAcqParameters	Return output bandwidth and sample rate in Hz.	None	bwHz_act: bandwidth. srSps: sample rate.
GetDiskFileInfo	Return info about file output operation.	None	fileinfo: see Appendix H: IQ Stream GetDiskFileInfo.
GetDiskFileWriteStatus	Determine if device is writing to disk. isComplete is more designed for triggering.	None	isComplete: always returns true after first writing to disk is complete. isWriting: returns true if writing to disk.
GetEnable	Determine if IQ stream processing is enabled.	None	enable: returns true if IQ stream processing is enabled.
GetIQData	Return IQ data in interleaved format.	buffer: buffer to store IQ data samples.	iqdata: I and Q data at alternating indexes in array. iqlen: number of IQ data pairs. iqinfo: see Appendix I: IQ Stream

			GetIQData.
GetIQDataBufferSize	Return maximum number of IQ sample pairs for GetIQData.	None	maxSize: maximum size of IQ data buffer.
GetMaxAcqBandwidth	Return maximum acquisition bandwidth.	None	maxBandwidthHz: maximum bandwidth
GetMinAcqBandwidth	Return minimum acquisition bandwidth.	None	minBandwidthHz: minimum bandwidth
SetAcqBandwidth	Set acquisition bandwidth in Hz.	bwHz_req: bandwidth.	None
SetDiskFileLength	Set how long to record to disk in milliseconds.	msec: number of milliseconds to record data.	None
SetDiskFilenameBase	Set name of file.	filenameBase: base filename for file output.	None
SetDiskFilenameBaseW	Set name of file.	filenameBaseW: base filename for file output.	None
SetDiskFilenameSuffix	Set suffix of file appended to name of file.	suffixCtl: suffix of file.	None
SetIQDataBufferSize	Set data buffer for IQ sample pairs.	reqSize: size of IQ data buffer.	None
SetOutputConfiguration	Set data type and output destination.	dest: destination for IQ sample output. dtype: IQ data type.	None
Start	Initiate IQ stream processing and data output.	None	None
Stop	Terminate IQ stream processing and data output.	None	None

Table 19. Playback Functions

Function Name	Description	Inputs	Outputs
GetReplayCompleted	Determine if file playback has completed.	None	complete: returns true if playback is complete
OpenDiskFile	Opens a .r3f file for playback and prepares for playback based on parameters.	filename: name of file to open. startPercentage: starting location in file for playback. stopPercentage: stopping location in file for playback. skipTimeBetweenFullAcquisitions: amount of time to skip in file. loopAtEndOfFile: enable/disable continuous looping of file. emulateRealTime: enable/disable real time emulation mode.	None

Table 20. Power Functions

Function Name	Description	Inputs	Outputs
GetHWStatus	Get any available battery HW info	None	powerInfo: see Appendix N: Power GetHWStatus.

Table 21. Reftime Functions

Function Name	Description	Inputs	Outputs
GetCurrentTime	Return Unix time and internal timestamp.	None	o_timeSec : Unix time. o_timeNsec : number of nanoseconds in specified second. o_timestamp : internal timestamp.
GetIntervalSinceRefTimeSet	Return number of seconds since internal API time and timestamp was set.	None	sec : number of seconds.
GetReferenceTime	Return Unix time and internal timestamp set by user.	None	refTimeSec : Unix time. refTimeNsec : number of nanoseconds in specified second. refTimestamp : internal timestamp.
GetTimeFromTimestamp	Convert internal timestamp to Unix time.	i_timestamp : internal timestamp.	o_timeSec : Unix time. o_timeNsec : number of nanoseconds in specified second.
GetTimestampFromTime	Convert Unix time to internal timestamp.	i_timeSec : Unix time. i_timeNsec : number of nanoseconds in specified second.	o_timestamp : internal timestamp.
GetTimestampRate	Return clock rate of device.	None	o_refTimestampRate : clock rate.
SetReferenceTime	Set Unix time and internal timestamp.	refTimeSec : Unix time. refTimeNsec : number of nanoseconds in specified second. refTimestamp : internal timestamp.	None

Table 22. Spectrum Functions

Function Name	Description	Inputs	Outputs
AcquireTrace	Acquire trace for spectrum.	None	None
GetLimits	Get Spectrum limits.	None	limits : see Appendix J: Spectrum GetLimits.
GetSettings	Get Spectrum settings.	None	settings : see Appendix K: Spectrum GetSettings.
GetTrace	Get specified Spectrum trace data.	trace : trace index. maxTracePoints : maximum number of trace points to retrieve.	traceData : spectrum trace data.
GetTraceInfo	Get spectrum trace information.	None	traceInfo : see Appendix L: Spectrum GetTraceInfo.
GetTraceType	Get specified Spectrum trace setting.	trace : trace index.	enable : returns true when trace is enabled.

			detector: detector type
SetDefault	Set Spectrum to default settings. See RSA_API documentation for more information.	None	None
SetSettings	Set Spectrum settings.	settings: See Appendix M: Spectrum SetSettings.	None
SetTraceType	Set specified Spectrum trace setting.	trace: trace index. enable: enable/disable trace. detector: detector type.	None
WaitForTraceReady	Wait for spectrum data to be ready, otherwise timeout.	timeoutMsec: maximum time to wait for data to be ready, in milliseconds.	ready: returns true when data is ready.

Table 23. Trigger Function

Function Name	Description	Inputs	Outputs
ForceTrigger	Force device to trigger.	None	None

Table 24. Trkgen Function

Function Name	Description	Inputs	Outputs
GetHWInstalled	Determine if tracking generator is installed	None	installed: returns true if tracking generator is found.

Appendix C: Error Values

The possible error return values are described below.

Table 25. Error Return Status Values

ReturnStatus	Description
noError	Function has succeeded.
errorNotConnected	Device is not connected.
errorTimeout	Timeout has occurred.
errorTransfer	Device communication failed.
errorFileOpen	File did not open.
errorParameter	Parameter has an invalid value.
errorDataNotReady	Data is not ready to be queried.
errorInvalidCalibConstantFileFormat	Calibration constant file format is invalid.
errorMismatchCalibConstantsSize	Calibration constant size is invalid.
errorFailed	Function failed.
errorCRC	Calculated CRC and saved CRC do not match.
errorWriteCalConfigHeader	Calibration configuration header failed to write.
errorWriteCalConfigData	Calibration configuration data failed to write.
errorReadCalConfigHeader	Calibration configuration header failed to read.
errorReadCalConfigData	Calibration configuration data failed to read.
errorEraseCalConfig	Calibration configuration failed to erase.
errorCalConfigFileSize	Calibration configuration size is invalid.
errorChangeToFlashMode	Device failed to change to flash mode.
errorChangeToRunMode	Device failed to change to run mode.
errorIncompatibleFirmware	Firmware is not up to date.
errorStreamADCToDiskFileOpen	Failure to open ADC streaming data file.
errorStreamADCToDiskAlreadyStreaming	Cannot change ADC file streaming parameters while streaming is active.
errorStreamADCToDiskBadPath	Nonexistent path or insufficient privileges to open file in specified path.
errorStreamADCToDiskThreadFailure	ADC streaming to disk thread failure.
errorRebootFailure	Failed to reboot instrument.
errorLOLockFailure	Local oscillator did not achieve lock.
errorPOSTFailureFPGALoad	Device internal HW configuration failure.
errorPOSTFailureHiPower	USB port power insufficient for device.
errorPOSTFailureI2C	Device internal control bus test failure.
errorPOSTFailureGPIO	Device internal data bus test failure.
errorPOSTFailureUsbSpeed	Device failed to connect as USB 3.0
errorPlaceholder	Error checking has not been implemented.
notImplemented	Function does nothing.

Appendix D: DPX GetFrameBuffer

Table 26. FrameBuffer Format

Field Name	Description
fftPerFrame	Number of FFTs performed in this frame.
fftCount	Total number of FFT performed since DPX acquisition started.
frameCount	Total number of DPX frames performed since DPX acquisition started.
timestamp	Acquisition timestamp for the current frame.
acqDataStatus	Acquisition data status for the current frame.
minSigDuration	Current minimum signal duration for 100% POI.
minSigDurOutOfRange	Minimum signal duration is currently out of range.
spectrumBitmapWidth	Width of the spectrum bitmap in pixels.
spectrumBitmapHeight	Height of the spectrum bitmap in pixels.
spectrumBitmapSize	Total number of pixels in the spectrum bitmap.
spectrumTraceLength	Number of trace points in spectrum trace.
numSpectrumTraces	Number of spectrum traces available.
spectrumEnabled	DPX Spectrum is enabled.
spectrogramEnabled	DPX Spectrogram is enabled.
spectrumBitmap	Vector containing the spectrum bitmap.
spectrumTraces	Vector containing the spectrum traces.
sogramBitmapWidth	Width of the spectrogram bitmap in pixels.
sogramBitmapHeight	Height of the spectrogram bitmap in pixels.
sogramBitmapSize	Total number of pixels in the spectrogram bitmap.
sogramBitmapNumValidLines	Number of valid lines in the spectrogram bitmap
sogramBitmap	Vector containing the spectrogram bitmap.
sogramBitmapTimestampArray	Vector containing the timestamps for each line in the spectrogram bitmap.
sogramBitmapContainTriggerArray	Vector containing the trigger events for each line in the spectrogram bitmap.

Appendix E: DPX GetSettings

Table 27. dpxSettings Format

Field Name	Description
enableSpectrum	Checks current status for DPX Spectrum.
enableSpectrogram	Checks current status for DPX Spectrogram.
bitmapWidth	Width of the spectrum bitmap in pixels.
bitmapHeight	Height of the spectrum bitmap in pixels.
traceLength	Length of the spectrum trace.
decayFactor	Current decay factor.
actualRBW	Current RBW value in Hz.

Appendix F: DPX GetSogramSettings

Table 28 sogramSettings Format

Field Name	Description
bitmapWidth	Width of the spectrogram bitmap in pixels.
bitmapHeight	Height of the spectrogram bitmap in pixels.
sogramTraceLineTime	Time per spectrogram trace line.
sogramBitmapLineTime	Time per spectrogram bitmap line.

Appendix G: IQ Block GetIQAcqInfo

Table 29. acqInfo Format

Field Name	Description
acqDataStatus	See RSA_API documentation for more info about bit masking.
acquisitionTimestamp	Timestamp of current IQ data.
acquisitionUnixTime	Unix time of current IQ data.

Appendix H: IQ Stream GetDiskFileInfo

Table 30. fileInfo Format

Field Name	Description
numberSamples	Number of IQ pairs written to file.
sampleOTimestamp	Timestamp of first sample written to file.
triggerSampleIndex	Sample index where trigger event occurred.
triggerTimestamp	Timestamp of the trigger event.
acqStatus	See RSA_API documentation for more info about bit masking.
filenames	Retrieve Data filename only. Header filename is currently not supported.
unixTime	Timestamp of first sample written to file.
triggerUnixTime	Unix time of the trigger event.

Appendix I: IQ Stream GetIQData

Table 31. iqInfo Format

Field Name	Description
timestamp	Timestamp of first sample of block.
triggerCount	Number of trigger events occurring during block.
triggerIndices	List of sample indices where triggers(s) occurred.
scaleFactor	Convert integer data types to standard voltage values.
acqStatus	Acquisition status flags to indicate block status. See RSA_API documentation for more information.
unixTime	Unix time of first sample of block.

Appendix J: Spectrum GetLimits

Table 32. limits Format

Field Name	Description
maxSpan	Maximum Span.
minSpan	Minimum Span.
maxRBW	Maximum RBW.
minRBW	Minimum RBW.
maxVBW	Maximum VBW.
minVBW	Minimum VBW.
maxTraceLength	Maximum trace length.
minTraceLength	Minimum trace length.

Appendix K: Spectrum GetSettings

Table 33. settings Format

Field Name	Description
span	Span of spectrum.
rbw	RBW of spectrum.
enableVBW	Check current status of VBW.
vbw	VBW of spectrum.
traceLength	Length of the spectrum trace.
window	Windowing used in spectrum. See RSA_API documentation for more information.
verticalUnit	Trace output unit (dBm, Watt, Volt, Amp, dBmV)
actualStartFreq	Actual start frequency set for spectrum.
actualStopFreq	Actual stop frequency set for spectrum.
actualFreqStepSize	Actual frequency step size set for spectrum.
actualRBW	Actual RBW set for spectrum.
actualVBW	Actual VBW set for spectrum.
actualNumIQSamples	Actual number of IQ samples set for spectrum.

Appendix L: Spectrum GetTraceInfo

Table 34. traceInfo Format

Field Name	Description
timestamp	Timestamp of first acquisition sample.
acqDataStatus	See RSA_API documentation for more info about bit masking.
unixTime	Unix time of first acquisition sample.

Appendix M: Spectrum SetSettings

Table 35. settings Format

Field Name	Description
span	Span of spectrum.
rbw	RBW of spectrum.
enableVBW	Check current status of VBW.
vbw	VBW of spectrum.
traceLength	Length of the spectrum trace.
window	Windowing used in spectrum. See RSA_API documentation for more information.
verticalUnit	Trace output unit (dBm, Watt, Volt, Amp, dBmV)

Appendix N: Power GetHWStatus

Table 36. powerStatus Format

Field Name	Description
externalPowerPresent	Status of external power connection.
batteryPresent	Battery installed.
batteryChargeLevel	Current charge of the battery in percent.
batteryCharging	Status of battery charging.
batteryOverTemperature	Battery overheating.
batteryHardwareError	Hardware error status from battery charging circuit